

Progenesis Installation Guide

Technical Support

If you have any problems or queries about this software our support team will be happy to help you.

Tel: +44 (0) 191 230 2121
Web: <http://support.nonlinear.com>
E-mail: support@nonlinear.com

Before installation

- Save your work and close all other programs.
 - You must be logged in with *Administrator* access rights to the computer. Please ask your local IT support if you're unsure whether or not you're logged on as an administrator.
 - You should have the installation CD and USB security dongle to hand.
-

Single license install of the Progenesis software

1. Insert the **Progenesis CD** into the CD-ROM drive.
2. Run the **setup.exe** from the CD to install the **Progenesis** software.
3. Launch the **Progenesis** software. (There will be a shortcut to the software on your desktop.)
4. Click the '**Install dongle driver**' link at the bottom of the screen. (If this link does not appear then the USB dongle drivers are already installed – skip to step 6).
5. This will activate the HASP device driver installation. The setup wizard will guide you through the install.
6. Insert the USB security dongle into a USB port.
7. You can now log off from the *Administrator* account and continue to use the software in your normal user account.

Network license install of the Progenesis software

1. Insert the **Progenesis CD** into the CD-ROM drive of the computer that will be running the HASP License Manager for the security dongle.
2. Browse the CD contents and double click the **Imsetup.exe** file to install the HASP License Manager.
3. During the installation ensure that the HASP License Manager is installed as a Service.
4. Finish the HASP License Manager install by choosing Yes to start License Manager.
5. Insert the USB security dongle into a USB port.
6. For every computer that will run the **Progenesis** software, insert the **Progenesis CD** into the CD-ROM drive. **Note:** this can include the computer that is running the HASP License Manager.
7. Run the **setup.exe** from the CD to install the **Progenesis** software.
8. Launch the **Progenesis** software. (There will be a shortcut to the software on your desktop.)
9. Click the '**Install dongle driver**' link at the bottom of the screen. (If this link does not appear then the USB dongle drivers are already installed – skip to step 11).
10. This will activate the HASP device driver installation. The setup wizard will guide you through the install.
11. You can now log off from the *Administrator* account and continue to use the software in your normal user account.

Running the **Progenesis** software for the first time:

1. Launch the **Progenesis** software.
2. Open or begin a new experiment. At this point the software will need to be licensed.
3. At the licensing section, which will appear automatically, ensure that the '**Using a network dongle**' option is selected within the **Dongle tab**.
4. Select the Domain that the computer running the HASP License Manager is on. If the computer is not on a Domain then skip this step.
5. Select the name of the computer that is running the HASP License Manager.
6. Click '**Apply**'.

Upgrading the Progenesis software

Option 1 – Automatic checking for updates

1. Launch the **Progenesis** software and click the 'check for updates' link found on the opening screen.
2. If you have a suitable Coverwise account and an update is available then you will be able to obtain the software update.
3. Download and Install the **Progenesis** software.

Option 2 – If you have received a CD with the new version

1. Insert the **Progenesis CD** into the **CD-ROM** drive.
2. If the installation does not begin automatically run the **setup.exe** from the CD to install the **Progenesis** software.

After the successful installation of the software your USB security dongle must be activated to run the new version. To do this:

1. Ensure the USB security dongle is connected to the computer.
2. Launch the Progenesis software. (There will be a shortcut to the software on your desktop.)
3. Open or begin a new experiment. At this point the software will need to be licensed.
4. At the licensing section, which will appear automatically, select the preferred method for updating your local or network dongle. These options are within the **Dongle tab**.

Installing a module onto the Progenesis software

1. Insert the **Security CD** into the CD-ROM drive of the computer that has the **Progenesis** software installed.
2. Ensure that the USB security dongle is connected to the computer.
3. Browse the CD contents and double click on the '**Progenesis Update**' file.
4. The module will now be available and fully licensed in the **Progenesis** software.